

# SUPPLEMENTAL LABELING

**DuPont Crop  
Protection**

**DUPONT™ LANNATE® LV  
INSECTICIDE  
POTATOES**

## DUPONT™ LANNATE® LV INSECTICIDE

EPA Reg. No. 352-384

### FOR USE ON POTATOES VIA OVERHEAD SPRINKLER IRRIGATION IN THE STATES OF COLORADO, IDAHO, NEBRASKA, OREGON AND WASHINGTON

#### RESTRICTED USE PESTICIDE

**Due to High Acute Toxicity to Humans.**

For retail sale and use only by Certified Applicators or persons under their direct supervision and only for those uses covered by the Certified Applicator's certification. Direct supervision for this product requires the certified applicator to review federal and supplemental label instructions with all personnel prior to application, mixing, loading, or repair or cleaning of application equipment.

#### DIRECTIONS FOR USE

It is a violation of federal law to use this product in a manner inconsistent with its labeling.

#### IMPORTANT

**BEFORE USING LANNATE® LV, READ AND FOLLOW ALL APPLICABLE DIRECTIONS; RESTRICTIONS; AND PRECAUTIONS ON THE EPA-REGISTERED LABEL.**

This bulletin contains new or supplemental instructions for use of these products in combination which does not appear on the package label. Follow the instructions carefully.

This labeling must be in the possession of the user at the time of pesticide application.

#### General Information

LANNATE® LV is a water soluble liquid that is applied by foliar application to control many important insect pests. LANNATE® LV is mixed with water for application.

#### Application Information, Rates and Timing

DuPont™ LANNATE® LV is recommended for control of aphids, potato tuberworm\*, loopers, beet armyworm, and fall armyworm in potatoes at the rate of 3 pints of product per acre applied through overhead sprinkler irrigation systems. Apply LANNATE® LV in 0.1 to 0.2 inches of water per acre.

Use of a wetting agent may improve performance. Make sequential applications at 5 to 7 day intervals or until insect populations are brought below threshold. Do not apply more than 15 pints (4.5 lbs a.i.) LANNATE® LV per crop to potatoes. Make the last application of LANNATE® LV at least 6 days before harvest.

\*Repeat applications of Lannate LV on a 5-7 day schedule, or longer as needed, to control tuberworm populations. An application schedule of effective insecticides with different modes of action may be needed to keep foliar feeding larval populations as low as possible prior to harvest to reduce the risk of larval damage to the tubers. Failure to adequately control tuberworm larvae prior to crop senescence or vinekill increases the risk of tuber damage.

#### Instructions for the Use of LANNATE® LV in Overhead Sprinkler Chemigation Systems.

##### Types of Irrigation Systems:

LANNATE® LV may be applied through overhead sprinkler irrigation systems for control of aphids, potato tuberworm, loopers, beet armyworm and fall armyworm in potatoes. The irrigation system used must provide uniform water distribution. Do not use filter screens smaller than 50 mesh throughout the system, due to possible build up of material on 100 mesh or smaller screens. Do not apply LANNATE® LV through any other type of irrigation systems.

© 2006 E. I. du Pont de Nemours and Company, Crop Protection, Wilmington, Delaware 19898

## **General Directions for Chemigation:**

### **Preparation**

A pesticide tank is recommended for the application of LANNATE® LV in chemigation systems. Thoroughly clean the injection system and tank of any fertilizer or chemical residues using a standard clean-out procedure. Dispose of any residues in accordance with State and Federal laws. Add 1/4 to 1/2 of the desired amount of water and then measure the required amount of LANNATE® LV into the tank. Complete filling the tank by adding the required amount of water. Agitate thoroughly to insure a uniform solution of LANNATE® LV. Once in solution, no further agitation is required. Injection solution should not be stored overnight. Highly alkaline water should be buffered so that the pH of the spray solution is in the range of neutral to slightly acidic (pH 5-7).

### **Injection Into Chemigation Systems**

Inject the proper amount of the LANNATE® LV solution into the irrigation water flow using a positive displacement injection pump. Injection should occur at a point in the main irrigation water flow to ensure thorough mixing with the irrigation water.

### **Uniform Water Distribution**

The irrigation system used for application of LANNATE® LV must provide for uniform distribution of LANNATE® LV treated water. Non-uniform distribution might result in crop injury, lack of effectiveness or illegal pesticide residues in or on the crop being treated. Ensure the irrigation system is calibrated to uniformly distribute the chemigation application to the crop. Contact the equipment manufacturer, the local University Extension agent or other experts if you have questions about achieving uniform distribution of the application.

### **Equipment calibration**

Calibrate the irrigation system and injector before applying LANNATE® LV. Calibrate the injection pump while the system is running using the expected irrigation rate. If you have questions about calibration, you should contact your state extension service specialists, equipment manufacturer or other experts.

### **Monitoring of Chemigation Applications**

A person knowledgeable of the chemigation system and responsible for its operation, or under the supervision of a responsible person, shall shut the system down and make necessary adjustments should the need arise. Wear the personal protective equipment as defined in the PPE section of the label for cleaners and repairers of application equipment when making adjustments or repairs on the chemigation system when LANNATE® LV is in the irrigation water.

### **Required System Safety Devices**

Do not connect any irrigation system used for pesticide applications to a public water system unless the pesticide label-prescribed safety devices are in place. Public water system means a system for the provision to the public of piped water for

human consumption, if such a system has at least 15 service connections or regularly serves an average of at least 25 individuals at least 60 days out of the year.

1. The system must contain a functional check valve, vacuum relief valve and low pressure drain appropriately located on the irrigation pipeline to prevent water source contamination from backflow.
2. The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump.
3. The pesticide injection pipeline must also contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.
4. The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops.
5. The irrigation line or water pump must include a functional pressure switch which will stop the water pump motor when the water pressure decreases to the point where pesticide distribution is adversely affected.
6. Systems must use a metering pump such as a positive displacement injection pump (e.g. diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.
7. Chemigation systems connected to public water systems must contain a functional, reduced-pressure zone, backflow preventer (RPZ) or the functional equivalent in the water supply line upstream from the point of pesticide introduction. As an option to the RPZ, the water from the public water system should be discharged into a reservoir tank prior to pesticide introduction.

There shall be a complete physical break (air gap) between the outlet end of the fill pipe and the top or overflow rim of the reservoir tank of at least twice the inside diameter of the fill pipe.

### **Posting of Areas to be Treated**

Posting of areas to be chemigated is required when 1) any part of a treated area is within 300 feet of sensitive areas such as residential areas, labor camps, businesses, daycare centers, hospitals, in-patient clinics, nursing homes, or any other public areas such as schools, parks, playgrounds, or other public facilities not including public roads, or 2) when the chemigated area is open to the public such as golf courses or retail greenhouses.

Posting must conform to all the following requirements. Treated areas shall be posted with signs at all usual points of entry and along likely routes of approach from the listed sensitive areas. When there are no usual points of entry, signs must be posted in the corners of the treated areas and in any other location affording maximum visibility to sensitive areas. The signs shall be printed in ENGLISH. Signs must be posted prior to application and must remain posted until foliage has dried and soil surface

water has disappeared. Signs may remain in place indefinitely as long as they are composed of materials to prevent deterioration and maintain legibility for the duration of the posting period.

All words shall consist of letters at least 2 1/2 inches tall, and all letters and the symbol shall be a color, which sharply contrasts with their immediate background. At the top of the sign shall be the words "KEEP OUT", followed by an octagonal stop sign symbol at least 8 inches in diameter containing the word "STOP". Below the symbol shall be the words "PESTICIDE IN IRRIGATED WATER".

Posting for chemigation does not replace other posting and reentry requirements for farm worker safety.

### **Operation**

Start the water pump and sprinkler, and let the system achieve the desired pressure and speed before starting the injector. Start the injector and calibrate the injection system according to the directions above. This procedure is necessary to deliver the desired rate per acre in a uniform manner. When the application is finished, allow the entire irrigation and injector system to be thoroughly flushed clean before stopping the system.

End guns must be turned off during the application, if they irrigate nontarget areas or if they do not provide uniform application and coverage.

It is recommended that nozzles in the immediate area of control panels, chemical supply tanks, wellheads and system safety devices be plugged to prevent contamination of these areas.

Do not apply when wind speed favors drift beyond the area intended for treatment.

Do not apply when system connections or fittings leak or when nozzles do not provide uniform distribution.

### **Cleaning the System**

Thoroughly clean the injection system and tank of any fertilizer or chemical residues using a standard clean-out procedure. Dispose of any residues in accordance with State and Federal laws. Consult your owner's manual or your local equipment dealer for cleanout procedures for your injection system.

Read the Limitation of Warranty and Liability on the Section 3 Federal product label before buying or using LANNATE® LV Insecticide. If terms are not acceptable, return the unopened package at once to Seller for full refund of purchase price paid. Otherwise, use by Buyer or any other User constitutes acceptance of the terms of the limitation of Warranty and Liability on the Section 3 Federal product label.

R-533 011306 04-20-06